

Exhibit F– Bluebeam Studio Tips and Tricks

Table of Contents 1

Section A: Tips for Reviewers 1

1.0 Add a Leader to a Callout..... 1

2.0 Delete a Leader from a Callout 1

3.0 Change Cloud Shape with Control Points..... 2

4.0 Delete Control Points within a Markup Cloud 2

5.0 Locate Comments Quickly using the Dimmer 2

6.0 Split the Screen to Compare Two Documents 3

7.0 Using Multiple Monitors to Compare Two Documents 3

8.0 Syncing Views on Split Screen Documents 4

9.0 Forwarding Comments – into a Revised Submittal 4

10.0 Snapshot Tool – to Copy an Area of the Page 5

11.0 Change the Color of a Pasted Snapshot 6

12.0 Page Overlay - for Original vs. Revised Page(s) Comparison 8

13.0 Document Comparison – to Compare entire Documents..... 10

14.0 Page Index – to Sort Pages in Markups List 11

15.0 Use Filters to Sort and Refine Markup Comments 13

16.0 Using the “My Tools” Toolset & Keyboard Shortcuts 14

17.0 Setting Temporary Scale of a Drawing Page for Dimensioning while in a Session 14

18.0 Calibrating Drawing Pages that have an Unknown Scale..... 15

Section B: Tips for Administrators & Support Staff 17

19.0 Archive Session Files & Comments: Copying Session Files to the Studio Project 17

20.0 Archive Session Files & Comments: Copying Session Files / Overwriting Project Files 18

21.0 Archive comments as an editable report table in Excel 19

22.0 Archive comments as a PDF report 22

23.0 Archive documents to Local Drive 25

24.0 Change Session Ownership 27

25.0 Grant Full Permission for Session 28

26.0 Studio Invite Groups..... 30


27.0 Scanned Document Prep..... 32

28.0 Image files to PDF:..... 33


Section A: Tips for Reviewers

1.0 Add a Leader to a Callout

- 1.1 Right-click on the callout
- 1.2 Click on "Add Leader"



- 1.3 Left-click to position additional leader




2.0 Delete a Leader from a Callout

- 2.1 Select the Callout
- 2.2 Hold your Shift Key down
- 2.3 Pick on the yellow grip at the tip of the leader you want removed.

3.0 Change Cloud Shape with Control Points

- 3.1 Select comment shape
- 3.2 Hold your Shift Key down
- 3.3 Pick a spot within any segment of the shape, the control point will be added.
- 3.4 Move control point to desired location



- 3.5 If required you can also right click on a line segment and select "Convert to Arc" to make round edges.



4.0 Delete Control Points within a Markup Cloud

- 4.1 Select cloud
- 4.2 Hold your Shift Key down
- 4.3 Pick on the control point you want to remove

5.0 Locate Comments Quickly using the Dimmer


Note: The Dimmer command can also be found in the "View" pull-down menu, or by pressing Ctrl-F5

- 5.1 The Dimmer button  fades the drawing contents to allow comments to be seen easier.




6.0 Split the Screen to Compare Two Documents

- 6.1 Open two documents for review
- 6.2 In bottom left corner of Bluebeam document window, click a split screen button. Split screen buttons include both Vertical split  and Horizontal split 
- 6.3 A second Bluebeam document window will open




7.0 Using Multiple Monitors to Compare Two Documents

- 7.1 Open documents for review
- 7.2 To drag a window to a second monitor, click the document tab at the top and drag
- 7.3 Hold and drag to second monitor
- 7.4 Double-click top of new window to make full screen



8.0 Syncing Views on Split Screen Documents


- 8.1 Select previous phase document
- 8.2 In bottom right corner of Bluebeam document window click Sync dropdown arrow
- 8.3 Check Page or Document
 - 8.3.1 Page will sync the movements of the current page being viewed
 - 8.3.2 Document will sync the movements of the current page and will also sync page turns of documents
 - 8.3.3 If sheets have been added in the new set this feature will not work



9.0 Forwarding Comments – into a Revised Submittal


Note: If comment has not been incorporated by the Design Team in the subsequent submittal

- 9.1 Highlight comment in the bottom markup list
- 9.2 Right-click comment on document above
- 9.3 Select copy



- 9.4 Select subsequent submittal document window
- 9.5 Paste Option 1: Right-click document where comment will be placed. Select paste
- 9.6 Paste Option 2: Press Ctrl-Shift-V. Markup will paste in exact same location from old to new page.
- 9.7 Paste Option 3: Click “Paste in Place” button . Markup will paste in exact same location from old to new page.
- 9.8 Edit FORWARDED comment as needed
- 9.9 Return to previous submittal
- 9.10 Go to status column
- 9.11 Double left-click highlighted area

- 9.12 Use the UCSD REVIEWER Menu
- 9.13 Select OPEN




10.0 Snapshot Tool – to Copy an Area of the Page

- 10.1 Select Snapshot tool from the top tool bar




- 10.2 Click and drag to create rectangular area to be copied



- 10.3 Selected area will be outlined in blue

10.4 Snapshots can be pasted back into Bluebeam or into other programs (Excel, Word, Outlook, etc.)



10.5 Paste the snapshot into the program and/or document


Note: Pasted snapshots will maintain the original scale and may need to be reduced in size

10.6 Click and drag from any corner to reduce size

11.0 Change the Color of a Pasted Snapshot


Note: See [Snapshot Tool](#) to first create a Snapshot. The color of the Snapshot can be changed to contrast against the page

11.1 Paste snapshot to desired location in document





11.2 Resize as needed

- 11.3 Click properties tab
- 11.4 Select Change Colors



- 11.5 Color Processing Window will open
- 11.6 Select Source Color: (typically Black)
- 11.7 This is the original color of the text






- 11.8 Select "To:" Color (Example: Red)
- 11.9 Confirm color change in Preview
- 11.10 Click OK


12.0 Page Overlay - for Original vs. Revised Page(s) Comparison

- 12.1 Open both documents to be overlaid
- 12.2 Click Overlay Pages button , or select Overlay Pages from Document pull-down menu




- 12.3 Overlay Pages window will open

- 12.4 Double-click either document to change parameters – ex. change pages option: All Pages, Current Page, or Custom Range, custom color for Page, etc.
- 12.5 Click OK to save parameter changes




- 12.6 A new PDF document will be created labeled Overlay, each document overlaid is now a separate layer
- 12.7 To turn layers on and off go to layers tab
- 12.8 Click eye image in box to turn off
- 12.9 Click box to turn on




13.0 Document Comparison – to Compare entire Documents

Note: Document comparison will only function if the Revised Document has the exact number of pages in the exact order. Page Overlay is the recommended way to compare document pages.


- 13.1 Open both documents to be compared
- 13.2 Select Compare Documents tool from top tool bar



- 13.3 Compare Documents window will open
 - 13.3.1 Note: Documents must have same page range to be compared
 - 13.3.2 Ensure Document A is the new phase
 - 13.3.3 Ensure Document B is the previous
- 13.4 Click OK to compare documents



13.5 New file will be created with changes clouded in red




14.0 Page Index – to Sort Pages in Markups List

Note: Adding the Page Index column in the Markups List will sort pages in the order they appear in the drawing set.


14.1 Select Markups List > Select Columns > Select Page Index from drop down

Subject	Page Label	Date	Comments
SD RHU	A-5.1 NEW ELEVATIONS CL...	10/16/2018 11:18:03 AM	NOW!!!! I AM
D - DS	T1.0 TITLE SHEET, INDEX T...	10/18/2018 8:47:48 AM	ejrlkgjllkeqjtk
	T1.0 TITLE SHEET, INDEX T...	10/18/2018 3:55:35 PM	6'-9"
SD RHU	A-5.1 NEW ELEVATIONS CL...	10/15/2018 9:03:41 AM	North Elevat
SD RHU	A-5.1 NEW ELEVATIONS CL...	10/15/2018 9:04:33 AM	Restricted Ar
SD RHU	A-5.1 NEW ELEVATIONS CL...	10/15/2018 9:23:37 AM	Restricted Ar

14.2 If Page Index is not listed go to Manage Columns




14.3 In the Manage Columns window, check Page Index



14.4 Click OK

14.5 Select Page Index Column to sort pages by the order they appear in the document




15.0 Use Filters to Sort and Refine Markup Comments

15.1 Standard Filters

15.2 Click Filter tab 

15.3 Select column to filter



15.4 Select funnel filter  to choose filter topic

15.5 Custom Filters

15.6 Click Filter tab

15.7 Select column to filter

15.8 Select drop down

15.9 Select "Custom"

15.10 Select Subject and choose search qualifier, ie equals, contains, ends with


15.11 Select search phrase

15.12 Select AND or OR to expand or restrict custom filter search

15.13 Select OK

16.0 Using the “My Tools” Toolset & Keyboard Shortcuts

The My Tools Toolset (at the top of the Tool Chest) has two big uses: storing a customized note, and creating a keyboard shortcut for frequently used markups



16.1 Adding a custom markup to My Tools (two options)

- 16.1.1 Create a custom note or other custom markup on the page
- 16.1.2 Click and drag the new markup from the page into My Tools (option 1)
- 16.1.3 Right-click on an existing markup (on the page) and select “Add to Tool Chest”, and select the My Tools Toolset (option 2)

16.2 Customizing My Tools

- 16.2.1 Double-click the new tool in My Tools to change it between Properties mode and Drawing mode.

Note: Markups in the Tool Chest can function in two different modes. Drawing mode creates an exact copy of the tool added to the Tool Chest (ex. a commonly-used text note added on multiple projects). Properties mode will create a new markup using the same visual properties of the original markup (ex. to create a keyboard shortcut to a commonly-use markup, like a callout).

16.3 My Tools Keyboard Shortcuts

- 16.3.1 When a tool is added to My Tools, it will automatically be assigned a keyboard shortcut number. Simply type that number (no enter or spacebar, just the number) to activate that tool going forward.

16.4 Sharing Custom Markups Between Departments

- 16.4.1 Create custom notes following the instructions above and add all notes to a page
- 16.4.2 Share the document with another user (outside of a Session)
- 16.4.3 The additional user can right-click the custom note and add to their My Tools tool set

17.0 Setting Temporary Scale of a Drawing Page for Dimensioning while in a Session


Note: Use this command to set a temporary Scale prior to any measurements of a drawing.

- 17.1 Locate the Floor Plans
- 17.2 Verify a scale is listed in the title of the Floor Plan on the Sheet




- 17.3 Within the “Measurements” panel  locate the Page Scale section
- 17.4 Set Precision to 1/2

17.5 Select the scale from the “Preset” Scales



Note: Once the scale has been selected for a page, that scale is temporarily stored in the page. After closing the file the scale will need to be reset.


17.6 To determine if page scales have been applied on pages, go to the Thumbnails. Check “Page Scale” in the Thumbnail Label Options to view page scales.



18.0 Calibrating Drawing Pages that have an Unknown Scale


Note: To use the Calibrate command there must be a known dimension on the page to reference. Use this command to set a Scale prior to any measurements of a drawing.

- 18.1 Locate page to calibrate
- 18.2 Within the “Measurements” panel  locate the Page Scale section
- 18.3 Set Precision to 1/2
- 18.4 Click the “Calibrate” button




Note: the Calibrate button works by selecting two points, and then entering the known distance between the two points. This sets a scale.

- 18.5 Locate a dimension or bar scale on the drawing. Select two points that are a known distance apart



- 18.6 Enter the dimension known on the drawing. This will set a scale on the sheet.




Section B: Tips for Administrators & Support Staff


19.0 Archive Session Files & Comments: Copying Session Files to the Studio Project

Note: This method copies files, including all markup comments, from the Bluebeam Studio Project to the Bluebeam Studio Session.

- 19.1 Join Session
- 19.2 Open Session document to be archived
- 19.3 Select Save AS (DMS) Icon



- 19.4 Save Project File window will open
- 19.5 Open to 2. Archive > Design > Design Management folder (Double-click parent folder to expand)
 - 19.5.1 Note: UCSD Version 1 and UCSD Approved files should be loaded to their respective archive folders




- 19.6 Name file with comment identifier (i.e Comments)
- 19.7 Click OK to save file to project folder

20.0 Archive Session Files & Comments: Copying Session Files / Overwriting Project Files

Note: This Section applies only to in a Linked Studio Project. A “Linked” Bluebeam Studio Project indicates a Studio Project where the files were added directly from the Studio Project to the Studio Session (right-click, add to new/existing Studio Session). The Bluebeam Studio Project and Bluebeam Studio Session must be linked in order to “update” from Session to Project.

Using this method will **OVERWRITE THE ORIGINAL STUDIO PROJECT FILES**. If the intention is not to overwrite the original files, or if the Session and Project are not linked together, refer to the previous Section, titled “Copying Session Documents to the Studio Project”. Also note that while Copying Session documents (described in the previous Section) is the preferred method, the method described in this Section is the faster method – because documents do not have to be opened before updating back to the Bluebeam Studio Project.


- 20.1 Join the Bluebeam Session
- 20.2 Identify the Session files to be
- 20.3 Copy the Session files back to the Studio Project
 - 20.3.1 Once QC is complete for each approved document: right click the file in the “Documents” area of the Session and select “Update Project Copy”




Note: The “Update Project Copy” command copies the file (including all markups) from the Session and replaces (updates) the copy of the file in the Bluebeam Project. Bluebeam Project has the ability to restore previous versions, so the original version of the file can be recovered if needed.

If the “Update Project Copy” option is not displayed when right-clicking the file, check the permissions of the studio account. Account email must have “Full Control” permission allowed.

- 20.3.2 Add a comment (optional) and Check In the document



- 20.3.3 After clicking “Update Project Copy”, Studio will display a message regarding updating the file located in Bluebeam Project
- 20.3.4 Once the file in Bluebeam Project is updated (may take several minutes), a notification is displayed at the bottom of the “Record” section within the Session log



- 20.4 Join the Bluebeam Project
- 20.5 Locate the updated files


Note: To verify the Project file has been updated, right-click the file and select “Revision History”. The latest version will be at the top of the list. Verify Date of Check In or comment.

#	Version #	Date	Operation	Email	Comment
3	1.2	6/9/2020 4:51:06 PM	Checked In	troy.barbu@aecom.com	Checked in from Session: QC'd by John Smith - Approved
2	1.1	6/5/2020 3:52:26 PM	Checked In	troy.barbu@aecom.com	Checked in from Session: Approved Set
1	1.0	6/2/2020 11:39:55 AM	Added	troy.barbu@aecom.com	


Note: Previous versions of the document can be recovered using the Revision History dialog

21.0 Archive comments as an editable report table in Excel


- 21.1 Filter as required, see Exhibit F1 for filtering
- 21.2 Click Summary Icon > Select CSV Summary from drop-down



21.3 Click the Column tab > Confirm desired columns are selected




21.4 Click the Filter and Sort Tab > Confirm filtering as desired, if additional filtering is required do so at this time




21.5 Export to the Bluebeam Studio Project

21.6 Select browse button next to export




21.7 Select Folder to Save To window will open



21.8 Select Project > Click OK

21.9 Select Project Folder to save to 2. Archive > Design > Design Management folder (Double-click parent folder to expand)


21.9.1 Note: UCSD Version 1 and UCSD Approved files should be loaded to their respective archive folders



21.10 Click Select Folder


21.11 Title Document as required

21.12 Click OK




22.0 Archive comments as a PDF report


- 22.1 Filter markups as required
- 22.2 Click Summary Icon > Select PDF Summary from drop-down



- 22.3 Click the Column tab > Confirm desired columns are selected




22.4 Click the Filter and Sort Tab > Confirm if additional filtering is required



22.5 Export to the Bluebeam Studio Project
22.6 Select browse button next to export




- 22.7 Select Folder to Save To window will open. Output can be exported to the Bluebeam Project or to a local drive
- 22.8 Title Document as required
- 22.9 Click OK




23.0 Archive documents to Local Drive


- 23.1 Join Bluebeam Studio Project
- 23.2 Go to Archive > Design > Applicable archive folder



23.3 Select file(s) for download, right-click, select download copy




23.4 Select location to save to (i.e. Desktop, downloads) and click Save.



24.0 Change Session Ownership


24.1 Go to studio.bluebeam.com

24.2 Login with Bluebeam Studio credentials




24.3 Select Session from list under My Sessions tab

24.4 Select Reassign Ownership tab




- 24.5 Enter email from new session owner
- 24.6 Click Apply



- 24.7 Ownership is now transferred permanently, and the session are removed from 'My Sessions' list.
- 24.8 Bluebeam Projects can also be transferred using the same procedure.


25.0 Grant Full Permission for Session

- 25.1 Select Session from Session list
- 25.2 Select Session name
- 25.3 Click Settings from drop-down menu



25.4 Go the Permissions Tab


25.5 Click Green Plus Icon



25.6 Add Users/Groups window will open


Note: Person requiring full permission must have attended the session previously

25.7 Select User from list



25.8 Click OK

25.9 Change Full Control for select name to Allow




25.10 Click Apply

25.11 Click OK


26.0 Studio Invite Groups

Note: An outlook invite group can be used to invite a group of people to a Bluebeam Studio Project to save time


26.1 Open Bluebeam and select project or session where contact group will need session invite and select invite icon invitation screen will open select from Address book




26.2 Changes browse location to local contacts list



26.3 Select invite group to add click To→ click okay list will add to invite screen



26.4 Click OK to load emails into the invite list



26.5 Click OK to send invite.


27.0 Scanned Document Prep

NOTE: Scanned documents are slow to regenerate in Bluebeam; therefore, all scanned documents are required to go through the preparation section. It is not recommended to work with scanned image copies of huge drawings as it can cause rendering issues.

27.1 Open the scanned PDF file

27.2 Export file to JPEG – Go the File Menu (located at the top of the Bluebeam screen)


- 27.3 Go to Export at bottom of menu
- 27.4 Select JPEG



- 27.5 Browser window will open
- 27.6 Select New Folder
- 27.7 Double left-click on the New Folder to open
- 27.8 Select Save


28.0 Image files to PDF:

28.1 Select Create from drop-down menu



28.2 Select from Multiple files

28.3 Browser window will open




28.4 Go to folder where files are located


28.5 Select image files you want to use

28.6 Select Open


- 28.7 Stapler dialog will open
- 28.8 Select 'Advanced...' Button



- 28.9 Select 96 dpi from the resolution image drop down
- 28.10 Select OK




- 28.11 Add a file name to the 'One Output File' field
- 28.12 Select Use source file folder




- 28.13 Click OK
- 28.14 Run Optical Character Recognition on Scanned PDF files
- 28.15 Go to Batch menu

NOTE: this Section requires Bluebeam eXtreme software version



- 28.16 Select OCR from the menu
- 28.17 Confirm all pages of open file
- 28.18 Set Language

- 28.19 Set Document Type to CAD Drawings
- 28.20 Check Detect Vertical Text
- 28.21 Check Detect text in pictures and drawings



28.22 Uncheck all other options & click OK